

Page Turning Pro for PDF

Making Page Turning e-Books from PDF format files!



www.page-turning-maker.com



About Page Turning Pro for PDF

Professional Page Turning Pro for PDF converter, is the best PDF to Flash Flip book solution for publishers to turn static PDF files into eye-catching flash flipping book in seconds. With using the page turning software, you can customize-designed flash book with build-in templates and themes. Moreover, you are able to insert rich-media to bring you flip book into a new level easily, no matter links, video, movie (Play FLV format), sound, etc. All features can be used easily. Download free trial to install and make a try!

Note: This product is distributed on a "Try before-you-buy" basis. All features described in this documentation are enabled. The registered version doesn't insert a watermark in your generated Page Turning Pro Books.



Key features of Page Turning Pro for PDF:

Product features:

Setting PDF file before import

- .Import file content from PDF file into pageflip book design interface smoothly
- .Import bookmark (table of content) from PDF file into Page Flip book easily
- .Import links (web links, page links, Email links) into your Flash Pro book
- .Allow to place a custom text or image watermark to PDF files
- .Enable your readers search the file content by input keywords
- .Customized the page ranges to import, including all pages (default selection), custom range, or only import 1-10 pages to initial preview
- .Setting page quality and size as you need
- .If you'd like to cut landscape pages into two portrait pages to spread in Flash Pro book, you should select the options of Detect wide pages

Define editing functions

- .Add links (web links, page links, and Email links) into pages
- .Add movie (only for FLV format) into pages
- .Add Image album on digital book, like your own photo or company images
- .Add SWF, make your pages more innervations
- .Add sound, setting player skin color when play/stop sound
- .Add YouTube video into flash pages
- .Add Printable Area, select printable area on pages
- .Add button, embed other action expect for above editing functions

Customize Page Flip Pro book appearance

- .Four Page Flip Pro book templates for you to choose: Classical, Float, Spread, Neat
- .Get more free themes online, just link to our website
- .Support to select button font and color
- .Support to select title and window's font and color
- .Support to select bookmark's font and color
- .Support to select search result font and font color
- .Setting background color between Gradient Color A and Gradient Color B, different Gradient Angle show different effect
- .Book Proportions, adjust page width and height on your Flash Pro book
- .Book Margins, allows to set the parameters of Top, Bottom, Left, Right Margin
- .Page Shadow, adjust left and right page shadow of your Page Flip Pro book
- .Right to left, allow your readers read flip book from the last page to first page
- .Hard Cover, turn the page like read a book



- .Single page, read pages one by one
- .Page number, apply for setting different page number types Roman number for catalogue, Arabic for main body
- .Minime style, only show e-book without toolbar and Triangle arrow
- .For protecting the content of flip book, you can create a password for all pages or customized page
- .Input your Google Analytics account ID, so you can monitor and analyze the traffic of your online flip book

Various output formats

- .HTML option, output HTML flipbook which can be viewed on PC online
- .ZIP option, allows to send flipbook via E-mail with zip format
- .EXE option, output it as stand-alone EXE for CD delivery
- .App option, support to use on Mac OS X system
- .Make Mobile Version, create mobile version Flash Pro book used for mobile phone (iPad, iPhone, Android) readers
- .Burn on CD, burn it to a CD/DVD or use it with an USB storage device

Other features

- .Batch convert PDF files to Page Flip book with real page effect
- .Command line entry mode: create e-books without opening window's desktop
- .Save and open the relevant setting obtains: Project, Theme, Language, and bookmark
- .Bookmark panel, select or delete bookmark, quickly name book title and move up/down title










Page Flip Pro book features:

Once your Page Flip Pro book finished, your viewer can be able to:

- .Share with others via E-mail, social website (like Facebook, Twitter, Digg, Linkedin, etc)
- .Browse Page Flip Pro book's title and logo (only in Float and Neat template)
- .Look for the current page number
- .Play or stop auto flip on your flip book
- .Turn on/off sound from Flash Pro book
- .Help icon, better tell readers how to use it by pop up message window
- .Enable readers to read in full screen mode
- .Zoom in/out both pages in Flash Pro book
- .Home button, allow readers link to your website after input page URL
- .Allow readers to print and download Page Flip Pro book
- .Switchable language icon, enables readers select one of languages which is set by publisher
- .Thumbnails navigation, helps to preview all pages and go to specific pages
- .Various page arrow provided: First, Previous page, Next page, Last page. Click on and go to the pages you want
- .Use mouse wheel, keyboard to get into the page directly



Quick Start


1. Launch the application via the desktop shortcut  ;
2. Click the "Import PDF" icon  to enter into Import PDF interface;
3. Click  icon to choose PDF file from your computer;
4. Click  icon to enter into template setting interface;
5. Choose template and set unique setting for eBooks, such as Tool Bar, Bookmarks, and then click the "Apply Change" icon  ;
6. Choose rich-media to insert on flip book from Edit pages interface, such as links, video, sound, movie, etc.
7. Click "Convert to Flipping Book" icon  to enter into Output interface;
8. Choose Output Type from HTML, ZIP and EXE, here take  as example;
9. Click  to set Output Folder as "C:\flash flip book", input File Name as "demo";
10. At last, click  icon to output created Page Turning Pro Book.



You can open the "flash flip book" folder in "C:", there are three files in this folder:



Open the "demo.html" file to view your created Page Turning Pro Book via Web Browser, such as Internet Explorer, Google Chrome, Firefox, etc.



Interfaces

There are some main interfaces you will see while using Page Turning Pro for PDF as below shows: **Application Options**, **Import PDF**, **Template Settings**, **Edit Pages**, **Language Option**, **Export Theme**, **Output**, **Batch Convert** and **Command Line**.




You can enter into each page to get clear instructions for every detail option.

I. Application Options Interface

1. Render Engine Option

Page Turning Pro for PDF Provides 3 different render engines for you to create higher quality Page Turning Pro Books, click "Options->Application Options" to enter into "Render Engine" interface:




SWF: Much legible characters, smaller output size
GPL Ghostscript: Higher color transfer quality
Inner Library: Faster convert speed
(Change option when PDF imported failed)

2. Create Mobile Version Option

(1) Pages Quality and Size

Five types of "Pages Quality and Size" for mobile version eBooks:






(2) Mobile Template


The current version provides two mobile template modes for you to use: Slide and Single Page Flip. The later one adds page-flipping effect on the pages while viewing in mobiles.

II. Import PDF Interface




Panel Description:

1. Source PDF File:




Click this icon to open the PDF file you want to convert;




View content of added PDF file to clarify before converting.

2. The Page Ranges to Import:




Convert all pages to Page Turning Pro Book;



2-5

Example: 1,3,5,9-21

Convert defined range page;



(Only import 10 pages to initial preview)

Just preview effect on first 10 pages.

3. Watermark




Add image or text watermark to flipping pages.




☒ Applying Watermark

Check this option first to choose default stamps or add new ones:



4. Page Quality

There are five types of "Quality and Size":



5. Other Options:

☒ Import bookmark

If your PDF file contains bookmarks, check this option to use in output Page Turning Pro Book;

☒ Import links

If your PDF file has links, check this to enable in flash flip book;

☒ Enable search

Check this option to enable search functionality in created flash flip book.


☒ Detect wide pages

Check this option to make landscape page in PDF file to be presented as two-page spread in output flash flip book.



At last, click  icon to enter into template setting interface.

III. Template Settings Interface




Page Turning Pro for PDF professional provides 4 different templates in the program: Classical, Float, Neat and Spread. Each template contains some unique settings, the below instructions will show you details about the default four templates.

The design setting interface contains below main parts:

Choose Template, Tool Bars Settings, Flash Display Settings and Flash Control Settings.


1. Choose Template



Click  icon to select templates from below interface:



PDF to Flash Flip Book Professional Utility User Document



Download more themes from Page-Turning-Maker now:
<http://www.page-turning-maker.com/templates-themes/index.html>.



Click this icon is to save current settings as a TXT file for later uses;



Click this icon is to import stored setting file at once.

2. Tool Bar Settings

<input checked="" type="checkbox"/> Tool Bar Settings	
<input checked="" type="checkbox"/> Title Bar	
<input checked="" type="checkbox"/> Buttons Bar	
Tool Bar on top	False
Add Icons Settings	
<input checked="" type="checkbox"/> Button Icons	

(1) Title Bar (only in Float template)

<input checked="" type="checkbox"/> Title Bar	
The Book Logo	C:\Users\Admini...
Logo URL	http://flipbuilder...
Book Title	<a href='http://...
Page Number Box On ...	False
page-turning-maker.com	Red Color

Customize book title and logo for showing on the top of your flash flip book. You are enabled to set the book title as HTML format text.

For example:

```
<a href='http://www.page-turning-maker.com'
target='_blank'>PAGE-TURNING-MAKER.COM</a> | <font color='#ff0000'
size='14'>Red Color</font>
```



(2) Buttons Bar


<input type="checkbox"/> Buttons Bar	
<input type="checkbox"/> Home Button	
<input type="checkbox"/> About Button	
Full Screen Button	Show
<input type="checkbox"/> Help Config	
<input type="checkbox"/> Print Config	
<input type="checkbox"/> Download setting	
<input type="checkbox"/> Sound	
<input type="checkbox"/> Zoom Config	
<input type="checkbox"/> Search	
<input type="checkbox"/> Share	
<input type="checkbox"/> Auto Flip	
Thumbnail Button	Enable
<input type="checkbox"/> Single Page	
<input type="checkbox"/> Language	

i. Home Button

You can add a home button  to help reader to click and go to your website directly:


<input type="checkbox"/> Home Button	
Home Button Visible	Show
Page URL	http://flipbuil...
Open Window	Blank

ii. About Button

Add About button  to show the author, contact, book, company info:

<input type="checkbox"/> About Button	
About Button Visible	Show
Content	<textformat ...

Click "... " to enter into "About & Contact" edit interface:



After clicking the About button, you will view the About window by clicking the button:






PDF to Flash Flip Book Professional Utility User Document




iii. Full Screen Button

To enable "Full Screen" functionality in output flash flip book, select "Show" in "Full Screen Button" option:



Then you can click icon  to view flash flip book in Full Screen, click icon  or "Esc" button to exit from the Full Screen.

Or if you want to show your flash flip book without Tool Bar while showing in Full Screen mode, you can set "No" in "Full Screen without Tool Bar" (just in Classical Template):



iv. Help Config

<input checked="" type="checkbox"/> Help Config	
Help Button	Show
Help Content File	-type.png ...
Help Window Width	400
Help Window Height	450
Show Help At First	Show

To show tips about viewing flash flip book, you can set "Show" in "Help Button" option, and you can define Help Content manually by inserting "Help Content File (image or SWF)", also enable to define the Width and Height of the Help image or swf. If you set "Book->Retain the book to center->No", you can set "Show Help At First->Show" to display the Help Panel with the Book as below:






You can also click the button  to view the same Help page in pop-up window.

v. Print Config

<input checked="" type="checkbox"/> Print Config	
Print Enable	Yes
Print Watermark File	ges\log.png ...

Choose "Yes" in "Print Enable", then click icon  to set print page range as below:




You can also click "Print Watermark File->..." button to choose image or SWF file from your computer as watermark on printed out pages.

vi. Download Setting

<input checked="" type="checkbox"/> Download setting	
Download Enable	Yes
Download URL	?PDFDemo.pdf

If you want your flash flip book readers to download the PDF file or the flash flip book directly from your website, select "Yes" in "Download Enable" option, then input the Download URL directly, you can use absolute path like "http://www.page-turning-maker.com/page-turning-maker/example/files/download/.pdf" or relative path like "/files/download/ Page-Turning-Maker Demo.pdf" (make sure you have uploaded the PDF to the same path).

Then readers can click the icon  to download your uploaded PDF file directly.


vii. Sound

<input checked="" type="checkbox"/> Sound	
Enable Sound	Enable
Sound File	mp3.mp3 ...
Sound Loops	-1


If you want to add background sound to your flash flip book, such as a song or other audio file, set "Enable Sound->Enable", then click "... " icon to choose "Sound File" from your computer, then set "Sound Loops", "-1" stands for playing the sound file all the time while viewing flash flip book, other value (N>0) stands for the times of playing the sound file.



viii. Zoom Config





To Enable Zoom In functionality, choose "Yes" in "Zoom in enable", then set "Zoom Scale", the value is the times between zoomed page size and the current page size.

In Float template, you don't need to set Zoom Scale, you can adjust more conveniently by the zoom in tool like this:  You can also set "Scroll with mouse->Yes" to scroll zoom in page while moving mouse.

ix. Search



Select "Show" in "Search Button" (make sure you have check "Enable Search" option in "Import PDF" interface), then define "Search Highlight Color", after clicking "Search" icon , you will see a popup box to input search words, then click Enter or "Search" button, you will get the below searching result:



x. Share



You can share via emails, or just through Facebook, Twitter, Google, etc..



a. Share Button

If you want readers to share via Email, you can enable "Share" feature as below shows:


<input type="checkbox"/> Share Button	
Share Button	Show
Email Subject	Rear my fl...
Email Body	{link}

When the viewers click the share button , they will enter into the Email interface with the link of your flash flip book in the Email body.

b. Social Share


If you want your flash flip book viewers to send the link to their friends or clients via Facebook, Twitter, Linkedin, Google, Yahoo and so on, you can add a Social Share button in your flash flip book for readers to send out your flash flip book link immediately:

Social Share Button	Show
---------------------	------

The readers just need to click the "Social Share" button , then the below window will pop up for them to choose share channel:



xi. Auto Flip


To auto flip your eBooks, you can set "Yes" in "Auto Flip->Enable" option; then define the Flip Interval (seconds of staying on each page); the value of "Play Count" stands for the times of auto playing the eBook, and "-1" stands for playing forever (after clicking the Auto Flip button , the flash flip books will be flipped by staying 3 seconds per page); if you want to auto start and flip the eBook after opening, just set "Auto flip when start up->Yes":

<input type="checkbox"/> Auto Flip	
Enable	Yes
Flip Interval	3
Play Count	-1
Auto flip when start up	Yes



xii. Thumbnail Button



Thumbnail Button	Enable
------------------	--------

Show Thumbnail Button  (set "Enable") to view page thumbnails of your book, or you can Disable it to hide the button.

xiii. Single Page


Single Page	Enable
-------------	--------


If your book contains landscape pages, or the page content is different to read for the font is too small, you can set "Single Page->Enable" to enable readers to click "Single Page"

icon  to view pages one after another, then click "Double Page" icon  to back to the normal book reading mode.

xiv. Language

Language	English
Language	English;Chinese...
Switchable	Yes

You can set language for showing tools or tips in your created flash flip book, click "..." to enter into "Language Settings" interface. You can choose two or more language to use, just check "Switchable" option, then users can click "Switch Language" button  to choose their prefer language for tips (more language setting details you can view in below Language Setting part):




(3) Tool Bar on Top (only in Float template)

If you want to place the toolbar in Float templates on the top of the flash eBook, you can set "Tool Bar on Top" as "True":



(4) Add Icons Settings

If you want to add some other kinds of buttons which the program doesn't provide, you can click "Add Icons Settings->..." to enter into "Icons Settings" interface to add new icons on tool bar:



You can define the link action as "Go to page", or open an online webpage, or even "Call Javascript function" to carry out your wanted interactive functionalities via defining Javascript function yourself.. After your "Apply Change", the new added icon will show in the toolbar. (More details about Call Javascript function will be introduced in the part of "Edit Page->Add Link".)

(5) Button Icons

Define settings for the icons of the buttons:

<input type="checkbox"/> Button Icons	
Icon Color	<input type="text" value="0xffffffff"/>
Icons File(SWF Only)	

i. Icon Color





ii. Icon File

Select the Tool Bar Button to replace with your own icon.

Icons File(SWF Only) C:\Users...

More details please view here:

<http://www.page-turning-maker.com/support/how-to-replace-icons-on-flash-toolbar.html>

3. Flash Display Settings

Flash Display Settings	
Retain the book to center	Yes
Font	
Initial Show	None
Show Corner Flip Effect	False
Background Config	
Flash Window Color	0x8fa0ab
Page Background Color	0xffffffff
Book Proportions	
Book Margins	
Page Shadow	
Hide Book Frame Bar	No
Right To Left	No
Hard Cover	No
Flipping Time	0.6
Page Number	
Minime Style	

(1) Retain the book to center

Retain the book to center Yes


If you select "No" in this option, the digital book will be shown on the right-side. This setting is for embedding special background image, such as advertisement or company log.

(2) Pages per thickness (only in Neat template)

To create more real life like e-book, you can set Pages per thickness, which means how many pages to show a distinguishable thickness. The smaller value set, the thicker your book. If the value is smaller than 0, or larger than the total page number of your book, it won't show any thickness. And on the book edge, you will see different page number tips for you to click and go to that page directly:



PDF to Flash Flip Book Professional Utility User Document



(3) Font

<input type="checkbox"/> Font	
<input type="checkbox"/> Buttons	
Font Color	<input type="text" value="0xffffffff"/>
Button Font	Tahoma
<input type="checkbox"/> Title and Windows	
<input type="checkbox"/> Bookmark	
<input type="checkbox"/> Search	

Change fonts of toolbar buttons, flash windows even bookmarks or search result panel.

(4) Initial Show (set in Float/ Spread templates)

You can show Bookmark panel or Thumbnails panel on the flash page at the beginning, just select "Bookmark" or "Thumbnails" in this option:

For Example, select "Thumbnails":



Then you will get flash flip book shown with below initial interface:






(5) Background Config

i. Background Color:




Define background for your flash flip book with gradient color or pure color (the same color for "Gradient Color A" and "Gradient Color B"). Gradient Angle is the angle between two colors.

ii. Background Image (set in Classical and Spread templates):



Click the icon "..." to choose background image from your computer, and there are 11 kinds of "Image Position" for you to choose: Scale to fit, Fill, Top Left, Top Center, Top Right, Middle Left, Middle Center, Middle Right, Bottom Left, Bottom Center and Bottom Right.

iii. Background Image (set in Float template):



The Float template enables you to add two background images: Outer Image and Inner Image. You can make Inner background image to show special information, such as advertisement or company logo, etc. There are also 11 kinds of "Image Position" for you to choose: Scale to fit, Fill, Top Left, Top Center, Top Right, Middle Left, Middle Center, Middle Right, Bottom Left, Bottom Center and Bottom Right.



(6) Flash Window Color



This color will be applied on all flash windows, such as the book window, "Help" window, "Print" window and so on.

(7) Page Background Color



When load pages, or if the page number of your PDF file is odd, then the page (the last page) will show with the "Page Background Color".

(8) Book Proportions



Please note that the values are not fixed in pixels or inches, they represent a ratio of "Page Width: Page Height", and the book size will be adjusted with your Explorer Window Size.



(9) Book Margins

i. Book Margin (set in Classical Template):



"Book Margin" refers to the distance between the book and the toolbar.

ii. Top/ Bottom/ Left/ Right Margin (set in Float/ Spread Template):



(10) Page Shadow

<input type="checkbox"/> Page Shadow	
Left page Shadow	50
Right page Shadow	25
Page Shadow Opacity	0.5

Left page Shadow



Right page Shadow

The value also takes the value of Book Proportions as reference, and the value interval of "Page Shadow Opacity" is "0~1", the larger value refers to the deeper shadow color.

(11) Hide Book Frame Bar

Hide Book Frame Bar

If don't want to show the book frame bar, choose "Yes" in this option.

(12) Right to Left

If the language of your file is read from right to left (such as Arabic), then choose "Yes" in "Right to Left" option:



(13) Hard Cover

If you want create hard cover effect (a book bound with rigid protective covers) for your flash flip book, choose "Yes" in "Hard Cover" option:



(14) Flipping time

Flipping Time	0.6
---------------	-----

Sets page flipping time in seconds according to your needs. (Recommended value is 0.6)

(15) Page Number

If you don't want to count in the cover page, table of contents pages into the actual page numbers, you can set "Start Page Numbering (Roman)" and "Start Page Numbering (Arabic)". For example, the first 3 pages are Table of Content pages with Roman page numbers, and set Arabic page numbers from page 4, then you will get page number box like below:

<input type="checkbox"/> Page Number	
Start Page Number (Roman)	0
Start Page Number (Arabic)	3
Front Cover Page:	
Pages:	I/8
The Fourth and Fifth Pages:	
Pages:	1-2/8



(16) Minime Style

If you want to present Page Turning Pro Book pages directly without showing toolbar, especially when you want to embed eBook into a small area in existing Web pages, then you can use this "Minime Style".

The Minime Style will trigger when the Width or Height of the Flash Container is less than the defined value. You can also always show the Page Turning Pro Book in Minime Style with adding a parameter to your URL like this:

www.yourdomain.com/index.html?alwaysMinimeStyle=true.




4. Flash Control Settings

<input type="checkbox"/> Flash Control Settings	
Security Settings	No Security
<input type="checkbox"/> Links	
Google Analytics ID	

(1). Security Settings

Security Settings	Single Pass ...
-------------------	-----------------

If you want to protect your flash books with passwords, you can click "..." icon to enter into "Flash Security Config" interface:



Select "Security Type->Single Password", and input passwords into the box (there is no restriction on password format at present). You can also set "Protect Page Range" as "All Pages" or the latter pages after a defined page number. (Tips: The program utilize RC4 algorithm to protect eBook pages, the eBook content pages will show nothing without permission.)



(2). Links



If you have checked "Import links" option in "Import PDF" interface, or add links in "Edit Page" interface, then you can define settings here, choose "Mouse over color", "Link alpha" (refers to the link area opacity, value interval: 0~1, "0" stands for the area is totally transparent), and "Open Window->Blank/ Self". The links also can be clicked after zooming by setting "Enable after Zooming in->Enable".

(3). Google Analytics



In the HTML output format, you can add statistics by using Google analytics. You can get more information about Google Analytics ID from <http://www.google.com/analytics/>.

Others, Theme (save and open setting)


If you want to save the current template settings as your own style template for later uses, you can click "File->Export current settings as Theme" button to storing all current template settings, include the background images, margin values, toolbar buttons and so on.

Then when you want to use later, just click "File->Import Themes", the theme will be added to the templates selecting interface.

Download more themes from Page-Turning-Maker now:

<http://www.page-turning-maker.com/page-turning-maker.com/themes-2012.html>.


After setting template and language, click



icon to apply the settings.





IV. Edit Pages

Use Page Turning Pro for PDF to edit imported pages directly, no matter you want to add link, video, sound or image file. Click "Edit Pages" button  to enter into page edit interface:



1. Add Link


Click the icon  and then draw a link box on the area you want to add link, then define properties in below panel:



You can define the link action as "Go to page", or open an online webpage, or even "Call Javascript function" to carry out your wanted interactive functionalities via defining Javascript function yourself.. For example, you can show a pop-up light box while readers clicking some image on pages, or pop-up a questionnaire or other Web Form by clicking some text. Just make sure the parameter you set in "Function" can be called in from HTML page.



Example: Check "Call Javascript function" as action type, then input Function as "testLightBox ("Hello, this is a test")":



And then make sure the Javascript wrote into the index.html page as below image shows (the same as you set in "Link Function"):



2. Add Movie




Click icon and then draw a box like below on the page you want to insert FLV movie:







Then you can select and edit the movie in below panel (define video player skin color, play and stop movie actions, etc.):




3. Add Image

Click the icon  to draw image box and then select image (.jpg, .png, .bmp), set Action Options (the same as Link Action Options):



4. Add Sound


Click the icon  to draw sound box and then select sound file, set other options:



5. Add Flash




Click icon to insert SWF flash into your defined area of flash flip book page:




6. Add Button



Click icon to draw an area for inserting your image or SWF button file with calling actions. The actions contain "Go to page", "Open a link", "Call Javascript function" and "Open Flash Window". The before three actions are the same with the actions in "Add Link", the "Open Flash Window" can help you to play SWF Flash or FLV Video in the pop-up window:




7. Add You Tube Video


Click the icon  and then draw a box on the page to insert You Tube video into pages directly. You just need to define the video ID directly. For example the video link is: <http://www.youtube.com/watch?v=xKA6WIqjB7c>, then the video ID is "xKA6WIqjB7c".





8. Add Printable Area

If you want readers can click on some area of your book to print the area directly, such as coupons which can be used to buy your presented goods, you can add a "Printable Area"

on pages by clicking the icon , and then draw the area on the pages, set title and description:





9. Copy and Paste


If you want to add same links, images, videos, audios to different pages, you don't have to repeat the "Link/Image/Video/Audio added" operations once and once again, just select the link object, click the copy button  and then go to the other page to click the paste button  directly.

10. Apply All

If you want to use the same link, video, audio, image or button on all pages (or all odd, even pages, or your customized pages), you can select the object and then click the Apply

All button , then define the apply page range in pop-up window like below:




After adding links, flash, movie or sounds, you can click the icon  to save the settings and back to the template setting interface.



V. Language Options Interface

Click "Option->Flash Language" or "... " button beside Language setting part, you will enter into the Language Settings interface as below shows:




Panel Description:


As the tips explaining, the "Labeled" column lists the buttons and instructions on Flash books in defined language, and the program provides you 10 different languages for you to use: English, Chinese, Arabic, French, German, Greek, Hebrew, Italian, Japanese and Portuguese.

You can also add other language for your own uses:

1. Click the button  and define name for the new language:



2. Choose the first label and click "Edit" icon, define new language text in "Labeled" box, then click "Save and Edit Next":



3. At last, you can get all Labels translated into your new language as the images shows:

Label	Labled
First Button	Première
Next Page Button	Page suivante
Last Button	Dernière
Previous Page Button	Page précédente
Download Button	Télécharger
Print Button	Imprimer
Search Button	Rechercher
Book Mark Button	Réservez Mark
Help Button	Aide
Enable FullScreen Button	Activer FullScreen
Disable FullScreen Button	Désactiver FullScreen
Sound On Button	Le Sound

You can delete unwanted language:




Or save your edited new language file as XML or TXT file:




Load language file saving before for current using:



After setting template and language, click  icon to apply the settings.



VI. Output Interface



Output types:

1. HTML



This output type is for uploading created Page Turning Pro Book onto websites:


You can define HTML Title and other properties by clicking "Advanced" button:



Set Keywords, Description or even Script in the below interface:



PDF to Flash Flip Book Professional Utility User Document



2. ZIP




This output type is for compressing the created files into an integral ZIP package which can be sending out as attachment directly. You can also define HTML Advanced

Settings by clicking "Advanced" icon:




Your recipients just need to unzip the ZIP file and then they can view the HTML flash flip book instantly:




3. EXE



This type is for outputting flash flip book as a single executive file, easy storing and easy viewing:



You can also define Icon and Opening Window Size in Advanced Settings:



4. APP



If you want to make executable application to run on Mac devices, you can output as "*.app" format.


5. Mobile Version



You can even output Mobile Version while choosing HTML or ZIP format at the same time.

After creating mobile versions, you just need to output all files online (including HTML, SWF, "files" and "mobile" folders), then you can visit the flash flip book page through your mobile browser.

6. Burn to CD



After choosing output type, then check the option "Burn to CD", set "CD Writer", define "Disc title".


How to make created eBooks available for others online, more details this support page:

<http://page-turning-maker.com/support/how-can-i-share-my-created-ebook-online.html>.

At last click  button to output flash flip book in your defined type.



VII. Batch Convert Interface



1. Add PDF Documents



Click this icon to add PDF files from computer;



Click this icon to add all PDF files in the folder (include sub-folders).

You can also remove some unwanted PDF, move up/ down files, or clear all documents.



2. Settings

(1). Output Settings

i. Choose Output Type




ii. Choose Output Path





You can also define output name pattern with FileName, Title, Subject and so on:




And after defining the File Name, you can preview the result example below:



iii. Define Output Option



Click "Advanced" icon to define Keywords, Description for HTML flash flip books, or define Icon, Window Size for EXE flash flip books:



iv. Merge All PDF Files to One Flip Book



(2). PDF Settings

i. Page Range




You can convert "All pages" or just "Custom range";



ii. Watermark




Click "Set Watermark" icon to enter into "Watermark" interface:



Check "Applying Watermark" option, then you can choose default stamps, Edit them, or Add Text Watermark, Add Image Watermark, Delete, Move Down/ Up.

iii. Page Quality



Choose quality and size type from listed five kinds.

iv. Other Options

☒ Import bookmark If your PDF file contains bookmarks, check this option to use in output Page Turning Pro Book;

☒ Import links If your PDF file has links, check this to enable in flash flip book;

☒ Enable search Check this option to enable search functionality in created flash flip book.

At last, click



icon to batch convert listed files

together.



VIII. Use Page Turning Pro for PDF in Command Line

You can also use Page Turning Pro for PDF in Command Line.

Page Turning Pro for PDF professional Command Line Usage:

PTCMD.exe [Options]

-f<PDF File> The source PDF file.

-o<output folder> Specify the folder for the output files.

-t[html|zip|exe] Output type. Default is html.

-n<OutputFileName> Specify the name for the output file.

-c<caption> Caption for HTML or EXE.

-s<Flash settings> Value format is:<Template name>#[<Theme name>|
<txt_setting file path>].

<Template name> could be: Classic, Float, Spread.

<Theme name> are list in the "Select a template"

window,

such as Blank, Blues, Nostalgia.

<txt_setting file path> is the file that you export
with "Save the template settings" function

-r<page range>. The page range that you want to import from PDF
File.

Range value string like:2-15,33,35-36,or All.(Default:
All)

-q<import quality> Count be 5,4,3,2,1.5 specify the higher quality
larger file size;1 specifies lower quality smaller file
size.(default:4)

-R<GS|SWF|LIB> Render engine options. (Default: GS, Ghostscript
render
engine)



- b<Y|N> Import bookmark yes or no. (Default: Y)
- l<Y|N> Import links yes or no. (Default: Y).
- S<Y|N> Enable searchable or not.(Default: Y, enable searchable)
- k<html key words> Set the keywords for html output file.
- d<html description> Set the descriptions for html output file.
- j<html javascript> Set the javascript for html output file.
- i<icon file path> Specify the icon path for exe output.
- w<window size> Specify the size of exe window.
Value could be: M,F, or some string like:800,600.
(width is 800,height is 600).

Examples 1:

```
PTCMD -f"C:\input.pdf" -o"C:\outputfolder" -n"index" -thtml -c"Title" -s"Float#c:\my_ebooksetting.txt" -r"1-8,9-14,42" -q4 -R"SWF" -bN
```

Examples 2:

```
PTCMD -f"C:\input.pdf" -o"C:\outputfolder" -n"ExeFileName" -texe -i"C:\app.ico" -c"Title" -s"Float#Blues" -r"All" -q5 -R"GS"
```

Examples 3:

```
PTCMD -f"C:\input.pdf" -o"C:\outputfolder" -n"index" -tzip -c"Title" -s"Float#Blank" -r"All" -q5 -R"GS" -k"html key words\"
```

Return Code:

- 1: Success
- 2: Input file not found
- 3: Parameters are invalid
- 4: Failed to load PDF
- 5: Failed to import bookmarks
- 6: Failed to import links
- 7: Failed to import searchable information
- 8: Failed to save the output file.



License Agreements

All copyrights to Page Turning Pro for PDF (the Software) are exclusively owned by Pageflippdf.com. For more information, visit our website at www.page-turning-maker.com.

Anyone may use this software but all the Page Turning Pro Books generated will automatically have a demo watermark on the first page of them. To remove the limitation you must register.

Once registered, the user is granted a non-exclusive license to use the Software on one computer (i.e. a single CPU) at a time. The registered Software may not be rented or leased, but may be permanently transferred, if the person receiving it agrees to terms of this license.

The Software unregistered (trial) version may be freely distributed, provided the distribution package is not modified. No person or company may charge a fee for the distribution of the Software without written permission from the copyright holder.

THE SOFTWARE IS DISTRIBUTED "AS IS". NO WARRANTY OF ANY KIND IS EXPRESSED OR IMPLIED. YOU USE AT YOUR OWN RISK. THE AUTHOR WILL NOT BE LIABLE FOR DATA LOSS, DAMAGES, LOSS OF PROFITS OR ANY OTHER KIND OF LOSS WHILE USING OR MISUSING THIS SOFTWARE.

You may not use, copy, emulate, clone, rent, lease, sell, modify, decompile, disassemble, otherwise reverse engineer, or transfer the licensed Software, or any subset of the licensed Software, except as provided for in this agreement. Any such unauthorized use shall result in immediate and automatic termination of this license and may result in criminal and/or civil prosecution.

All rights not expressly granted here are reserved by Page-Turning-Maker.com Solution.

Installing and using the Software signifies acceptance of these terms and conditions of the license.

If you do not agree with the terms of this license you must remove the Software files from your storage devices and cease to use the product.



How to Order

Order Online

(<http://www.page-turning-maker.com/page-turning-maker.com/order.html>) or Order Toll Free 1-877-353-7297 (When you order toll free just give the operator the product number of the product you would like).

How to purchase online?

1. Select a license type above, and click [Buy Now]
2. Select the currency that you want to use. (You can also continue shopping)
3. Fill billing information and select a payment method. (Your information is safe with us)
4. Check the information you filled previously and click "Place Secure Order"

Other Order Ways—With Phone/Mail/Fax/Check:

If you are not comfortable ordering online with a credit card, you are welcome to choose an offline order option in the payment section of the order process. We accept mail, fax, wire, and PO (if applicable) ordering options in addition to ordering online. We also provide phone orders through our 24x7 order desk at 1-877-353-7297, or (952) 646-5331 for International Callers.

Please note that all of the offline ordering options do have additional fees for processing. To place an order by mail, fax, wire, and PO (when applicable), use the online form and then choose one of these payment options found in the Payment Method section of the form. Once submitted online, the appropriate information will be provided to you in your web browser to send your payment to us offline.

100% unconditional 30 Day Money Back Guarantee

Want to custom the program or have other questions about purchase?

Support at support@page-turning-maker.com .



Support

You can easily search or browse our frequently asked questions, and learn tutorials about products, and get your registration code back. If you are not satisfy with the solutions provided, please contact support team for help.

1. Frequently Asked Questions

You can find answers to questions about technique issues here:

[http:// www.page-turning-maker.com\page-turning-maker.com\general-support.html](http://www.page-turning-maker.com/page-turning-maker.com/general-support.html).

2. Get lost license code

Click here to look up the order » (<http://www.regnow.com/cs/orderStatus>)

You can pull up a copy of your order by entering your email address. After you find your order, you may view its status, view details of your order (including the license key), and obtain the invoice.

3. Contact Us

If you have other questions or requirements, contact us directly through our support

Email: support@page-turning-maker.com, we will respond you ASAP.



<http://page-turning-maker.com>

